Manual

XELA Sensor Server Standalone for Linux and Windows v.1.4.0

Table of contents

Table of contents	
Using the Server	3
Prerequisites:	3
Set up	4
Manual	4
Arguments	5
How to use XELA Logger	6
Configuration file format	7
Data format	8
Supported USB-CAN devices	9
Example usage:	10
Common errors	11

Using the Server Prerequisites:

Primary requirement is to run the code with **Python 3.7.5** as the files have been pre-compiled and therefore might give an error if running on different Python version

The following packages are required to run the sensor service and tools:

- 1) Tkinter
- 2) numpy
- 3) matplotlib (version 3+ recommended)
- 4) python-can
- 5) psutil (normally installed)
- 6) python-socketio
- 7) asyncio (requires Python 3.7+)
- 8) uvicorn

Set up

Manual

Unpack the files to suitable location.

Run configuration tool for can

Windows PowerShell: ./xela_conf.exe Windows cmd: xela_conf.exe

Linux: ./xela conf

Run the server

Windows PowerShell: ./xela_server.exe Windows cmd: xela_server.exe

Linux: ./xela_server

Run the visualizer

Windows PowerShell: ./xela_viz.exe

Windows cmd: xela_viz.exe

Linux: ./xela_viz

Run the logger

Windows PowerShell: ./xela_log.exe

Windows cmd: xela_log.exe

Linux: ./xela_log

Arguments

Following is the list of arguments that can be given to the executables (green – used, red – not used):

-f *filename* The name of configuration file (with .ini extension) to be used (full path or just name if in same folder) (default: /etc/xela/xServ.ini (Linux) or xServ.ini (Windows)

```
Usage: [xela_conf, xela_log, xela_server, xela_viz] Example: ./xela server -f myconf.ini
```

--ip *ip* The IP address for the computer running the server (if same computer, it would be 127.0.0.1 aka *localhost*)

```
Usage: [xela_conf, xela_log, xela_server, xela_viz] Example: ./xela_viz --ip 192.168.0.107
```

-p port The port for communicating the server (default: 5000)

```
Usage: [xela_conf, xela_log, xela_server, xela_viz] Example: ./xela viz -p 5007
```

--viz <u>sensor_number</u> The sensor number to display in visualization (throws an error if sensor doesn't exist)

```
Usage: [xela_conf, xela_log, xela_server, xela_viz] Example: ./xela_viz --viz 3
```

-s sensor_config The string for configuring logging script (default: 1:100) more info in How to use XELA Logger

```
Usage: [xela_conf, xela_log, xela_server, xela_viz] Example: ./xela_log -s 1-3:1000
```

--log *log_file* The path to log file (default: /etc/xela/LOG/app.log in Linux or LOG/app.log in Windows where app corresponds to app name) more info in How to use XELA Logger

```
Usage: [xela_conf, xela_log, xela_server, xela_viz] 
Example: ./xela_server --log my_server_log.log
```

-d device The can device name (default: socketcan in Linux or esd in Windows)

```
Usage: [xela_conf, xela_log, xela_server, xela_viz] Example: ./xela_conf -d pcan
```

-c channel The can device channel (default: can0 in Linux or 0 in Windows)

```
Usage: [xela_conf, xela_log, xela_server, xela_viz] Example: ./xela conf -c PCAN USBBUS1
```

How to use XELA Logger

Under the -s flag (stands for sensor config), you can write the info in following formats that can be combined:

Data	Meaning
1	Sensor* 1 will be read (default 100 broadcast cycles*)
1,2,3	Sensors 1, 2 and 3 will be read (default 100 broadcast cycles)
1-3	Sensors 1,2 and 3 will be read (default 100 broadcast cycles) (shortcut)
1:150	Sensor 1 will be read 150 broadcast cycles
1:150,2	Sensor 1 will be read 150 broadcast cycles and sensor 2 for default 100
1-3:150	Sensors 1, 2 and 3 will all be read for 150 broadcast cycles
1-5,2:150	Sensor 2 will be read 150 broadcast cycles and sensors 1, 3, 4 and 5 for default 100
1:60t	Sensor 1 will be read for 60 seconds
1-3:30t	Sensors 1, 2 and 3 will all be read for 30 seconds
1-5,2:30t	Sensor 2 will be read for 30 seconds and sensors 1, 3, 4 and 5 for default 100 broadcast cycles
1-5:200,3:30t	Sensor 3 will be read for 30 seconds and sensors 1, 2, 3 and 5 will all be read for 200 broadcast cycles

Note

^{*}If sensor is defined multiple times, latest entry counts

^{*}Sensors can be from 1 to 16

^{*}Broadcast cycles depend on the sensor and computer configuration and is defined as sensor read cycle and backup update cycle combined

Configuration file format

Due to the limitations of the esd CAN-USB device driver you are unable to use automatic configuration tool

[CAN] bustype = socketcan *1 channel = can0 *2 [viz] max offset = 40 *3 max size = 50 *4[sensor] num brd = 2^{*5} brd height = 4 *6 brd width = 4^{*7} ctrl id = 6*8m = 5 *9 $chan = 0^{*10}$ [sensor2] brd height = 4brd width = 6ctrl id = 7m = 5chan = 0mirror $x = 1^{*11}$ mirror y = 1 *12 rotate = 2^{*13}

```
Sections in config file:
```

[CAN] - defines section for CAN bus
[viz] - defines settings for visualization
[sensor] - defines primary sensor settings and number of total boards
[sensorM] - (N is a number above 2, sequential) - defines Nth sensors settings, if different from primary

Notes:

- *1 Bus types for Linux are socketcan, slcan and pcan and for Windows esd, pcan
- *2 Channel for **pcan** is *PCAN_USBBUS1*, for **socketcan** can0 and for **esd** 0
- *3 Defines how far the bubbles will go in visualization
- *4 Defines how big the pressure bubble will be
- *5 Defines the total number of boards
- *6 Defines the number of rows on the sensor (visually only)
- *7 Defines the number of columns on the sensor
- *8 Defines controller ID
- *9 Defines sensor mode (default: 5)
- *10 Defines channel (default 0, in multi-mode (2 sensors on one controller) use 2 for second sensor)
- *11 Defines for visualizer to mirror display of taxels on x-axis (optional)
- *12 Defines for visualizer to mirror display of taxels on y-axis (optional)
- *13 Defines for server to rotate the sensor by 180 degrees before outputting the data (optional)

Data format

As the data is provided in a JSON string, there are few ways to access it and it has following format:

```
{'data':'FA00,FA00,FA00,FB00,FB00,FB00...', 'sensor': '1'}
```

data contains X, Y and Z values in HEX and they are comma-separated for all taxels on a sensor

sensor has the number of the sensor in string format (important when requesting multiple sensors from server)

Supported USB-CAN devices

Following USB-CAN devices are supported in Linux:

- esd CAN-USB/2 (bus: esd)
- PEAK USB-CAN (bus: pcan, default channel: CAN_USBBUS1)
- CANable and CANable Pro (with candlelight firmware on Linux)

Example usage:

```
#!/usr/bin/env python3
import asyncio
import socketio
loop = asyncio.get_event_loop()
sio = socketio.AsyncClient()
@sio.event
async def connect():
 print("Connection established")
@sio.event
async def sensor_data(data):

#normally the taxel data is in data element as list type string
  print(data[u"data"])
@sio.event
async def disconnect():
  print("Disconnected from server")
async def start_server():
  #using loop makes the application wait for connection in case server takes too long to start
  ncd = True
  while ncd:
       await sio.connect("http://localhost:5000", namespaces=["/sensor1"])
     except socketio.exceptions.ConnectionError:
       pass
     else:
       ncd = False
       break
  try:
     await sio.wait()
  except KeyboardInterrupt:
     exit()
loop.run_until_complete(start_server())
```

Common errors

Error	Reason
Module not found	Use pip to install the mentioned module and try again. If the module is already installed, try reinstalling. On systems with several Python versions, you might need to specify which pip you are using
Could not start CAN: OSError: [Errno 19] No such device	Make sure to pull up the network with one of the following commands, if using Linux:
	user@localhost:~\$ sudo ip link set can0 type can bitrate 1000000 user@localhost:~\$ sudo ip link set up can0
	or
	user@localhost:~\$ sudo slcand -o -s8 -t hw -S 3000000 /dev/ttyUSB0 user@localhost:~\$ sudo ifconfig slcan0 up
	In case of Windows, make sure the adapter is connected and using specified channel (esd channel might not be 0)
The MATPLOTLIBDATA environment variable was	This can be ignored as it is caused by incompatibility between PyInstaller and MatPlotLib
deprecated in Matplotlib	meompationity between rymstaner and Matriotelb
3.1 and will be removed in 3.3	For future builds we will try to remove the warning by modifying the libraries involved.

If you find errors, not listed in this file, please send an email regarding it to info@xelarobotics.com

Do not forget to attach files from /etc/xela/LOG folder in Linux or LOG folder in Windows (if using default log folder) with the terminal log (if you copy-paste, there might be some strange characters, don't worry about them, we can read them) and description of the failure. If you have made your own code that is causing errors, please attach it as well.